



Common Component

[Badge](#)[Banner](#)[Bottom Navigation](#)[Bottom Sheet](#)[Buttons](#)[Chips](#)[Controls](#)[Dialog](#)[Empty](#)[Text Inputs](#)[List Header](#)[Search Bar](#)[Page Indicator](#)[Popup](#)[Profile](#)[Progress Indicator](#)[Spinner](#)[Tabs](#)[Top Navigation](#)[Video Player](#)

Contents Component

[Card](#)[Image Grid](#)[List](#)


Chatroom Component

[Flex Message](#)

Top Navigation

Top Navigation shows the title of the screen where the user is remaining and key action buttons.

Anatomy



1. Title

This is the place where the title of the page is located.

2. Left Button area (Optional)

Place the buttons related to navigation (e.g. Back, Cancel).

3. Right Button area(Optional)

Place the actions buttons related to the screen. (If there are two or more buttons, place the most frequently used buttons to the left side of this area)

Provide from the far right side by including in the "Overflow" button if there are many actions available.

4. Container / Background area


This is the background area of Top Navigation.

Types


Top Navigation can be classified into three types based on usability.

Empahsis type

[Light](#)[Dark](#)




- As the type applied to the top-level screen on the important pages of LINE app, the boldfaced title is indicated on the left and the option buttons are provided on the right.
- The title can function as a tab or also play a role of unfolding the menu option as shown in the example.
(Using two tabs is recommended.)



Do


Although Top Navigation is placed as same elevation as the initial content, the elevation increases for distinction from the content when scrolled, and the content is scrolled back.





Don't


If title is used as tab, take a precaution to prevent from having more than two tabs. Three or more title tabs make the screen complicated.

Regular type






- This is the type applied to the screen after the entry of depth from the top-level screen.
- You can place the title at the center and provide icons or a text button on the left/right.





Do

Place the frequently used action buttons from the left when you place buttons on the Right Button area. You can insert the actions with somewhat low priority below the Overflow button.



Caution

If Icon button and Text button are combined in the Right Button area, this can harm the visual consistency and also cause a multilingual support problem.




Do

The action name can be a title, or the number of selected items can be indicated in case of selective actions.

Caution

Avoid underlining the title because it declines clarity and also can cause misunderstandings.

Search type



- If search is the most important task on the screen, this type can be applied to the top navigation.
- In the search mode, top navigation elements other than the Search bar will be concealed.





Search Bar

Further details on the Search Input are available in Search Input.

Usage


General Usage





If you tap the button on the top-level screen to enter the lower depth screen, the regular type top navigation will be exposed.


Bottom Sheet Usage




Place in the bottom sheet header to enable the performance of tasks in the sheet.

Interaction


Flexible Header





- The top navigation size can be increased after being decreased according to the scrolled direction.
- The buttons may be omitted when the size is decreased.


Scroll with Search bar



scroll up You can hide the search bar to the area below the top navigation.

scroll down The search bar will reappear.


Placement



Placement Place right below the status bar which is the very top section of the app screen.

Design Guide Its location cannot be changed and no design QA is requested for its location.

Bottom Sheet



Placement Used for the header at the very top section of the bottom sheet.

Design Guide Its location cannot be changed and no design QA is requested for its location.

